# pysimCoder

# Step-by-step Installation in Ubuntu with Anaconda

by

Felipe Depine and Roberto Bucher

January 21st 2025

### Step 1: "Basic Installation"

- a) uname -r
- b) sudo su
- c) apt-get install linux-headers-6.8.0-51-generic
- d) apt-get install make

#### Step 2, part c:

```
emb@emb:~$ uname -r
6.8.0-51-generic
emb@emb:~$ sudo su
[sudo] password for emb:
root@emb:/home/emb# apt-get install linux-headers-6.8.0-51-generic
```

# Step 2: Install Anaconda

Link: https://docs.anaconda.com/anaconda/install/


# Step 3: Install Slycot and Python Control

Link: https://python-control.readthedocs.io/en/latest/intro.html

#### Step 4: Download files

Link: https://www.robots5.com/






# Step 5: "Additional files for Python and pysimCoder"


- a) mkdir Develop
- b) cd Develop
- c) Copy files to Develop
- d) make packages

#### Step 3, part c:



# Step 6: "pysimCoder"


a) make pysimcoder



#### Step 7: "Install SHV"

- a) make Shv
- b) Start a new terminal as "normal user"
- c) cd pysimCoder/CodeGen/LinuxRT/devices
- d) make SHV=1


Step 5, part a: D:~/Develop\$ make Shv



## Step 8: "Install NuttX"

- a) make nuttx
- b) make f7
- c) Configure "make menuconfig" to match the target needs (next slides)

Step 6, part a: :~/Develop\$ make nuttx



#### Step 8: Continuation "Install NuttX"

Optional
Procedures
depending on
target needs.

```
emb@emb: ~/Develop/NUTTX/nuttx
                    NuttX/x86 64 Configuration
Arrow keys navigate the menu. <Enter> selects submenus ---> (or empty
submenus ----). Highlighted letters are hotkeys. Pressing <Y>
includes. <N> excludes. <M> modularizes features. Press <Esc> to
exit. <?> for Help. </> for Search. Legend: [*] built-in []
       License Setup --->
       Build Setup --->
       System Type --->
       Board Selection --->
       RTOS Features --->
       Device Drivers --->
       Networking Support --->
       Crypto API --->
       File Systems --->
       Graphics Support --->
     <Select>
                 < Exit >
                             < Help >
                                        < Save >
                                                    < Load >
```

Go to "System Type", then "Timer Configuration"

#### Step 8: Continuation "Install NuttX"


Optional Procedures depending on target needs.

```
PWM low-level operations
[*] TIM1 PWM
     TIM1 Mode
    TIM1 Lock Level Configuration
    TIM1 t DTS Division
(10) TIM1 Initial Dead-time
     TIM1 Channel 1
     TIM1 Channel 1 Mode
     TIM1 Channel 1 Output
      TIM1 Channel 1 Complementary Output
     TIM1 Channel 2
     TIM1 Channel 2 Mode
     TIM1 Channel 2 Output
      TIM1 Channel 2 Complementary Output
     TIM1 Channel 3
     TIM1 Channel 4
     TIM1 Channel 5 (internal)
     TIM1 Channel 6 (internal)
   TIM2 PWM
 1 TIM3 PWM
1 TIM4 PWM
[*] PWM Multiple Output Channels
[ ] TIM PWM TRGO support
[ ] TIM1 ADC
[*] TIM2 ADC
     Select TIM2 ADC channel (TIM2 ADC channel 1) --->
[ ] TIM3 ADC
[ ] TIM4 ADC
(5000) ADC1 Sampling Frequency
(1) ADC1 Timer Trigger
[ ] TIM1 Capture
[ ] TIM2 Capture
[ ] TIM3 Capture
[ ] TIM4 Capture
   STM32 TIMx Outputs Configuration --->
```

```
PWM low-level operations
[*] TIM1 PWM
    TIM1 Mode
     TIM1 Lock Level Configuration
   TIM1 t DTS Division
(10) TIM1 Initial Dead-time
    TIM1 Channel 1
     TIM1 Channel 1 Mode
       TIM1 Channel 1 Output
      TIM1 Channel 1 Complementary Output
     TIM1 Channel 2
     TIM1 Channel 2 Mode
     TIM1 Channel 2 Output
       TIM1 Channel 2 Complementary Output
     TIM1 Channel 3
     TIM1 Channel 4
     TIM1 Channel 5 (internal)
     TIM1 Channel 6 (internal)
   TIM2 PWM
   TIM3 PWM
   TIM4 PWM
[*] PWM Multiple Output Channels
   TIM PWM TRGO support
 1 TIM1 ADC
[*] TIM2 ADC
     Select TIM2 ADC channel (TIM2 ADC channel 1) --->
[ ] TIM3 ADC
[ ] TIM4 ADC
(5000) ADC1 Sampling Frequency
(1) ADC1 Timer Trigger
[ ] TIM1 Capture
[ ] TIM2 Capture
[ ] TIM3 Capture
[ ] TIM4 Capture
   STM32 TIMx Outputs Configuration --->
```

Uncheck complementary outputs for TIM1

#### Step 8: Continuation "Install NuttX"



Save as .config and exit

### Step 9: Continuation "Install NuttX"

- d) Start a new terminal as "normal user"
- e) cd pysimCoder/CodeGen/nuttx/devices
- f) make SHV=1

:~/Develop/pysimCoder/CodeGen/nuttx/devices\$ make SHV=1

## Step 10: "Configure SHV Application"

- a) Set user and password in the shvspy window
- b) User: admin
- c) Password: admin!123

# Step 11: "pyshv module"

a) sudo pip install pyshv

Done, installation is complete!